

# Bode Analyzer Suite 3.25 SR2

## Bugfixes from version 3.25 SR1 to 3.25 SR2

Bug ID	Description
247497	Anti-Aliasing can't be disabled because level in options can't be set to zero
247708	BAS sometimes crashes during measurement initialization

## Known Issues

Known issues in **Bode Analyzer Suite 3.25 SR2** that will be resolved in future:

Bug ID	Description	Current workaround
184547	Recalculate measurement trace values retroactively can lead to deviation at frequencies below 100 Hz	Don't use feature "Recalculate measurement trace values" for measurement data below 100 Hz
286941	Copying a memory breaks admittance and reflection calculation	If you use reflection or admittance, don't copy and paste or drag and drop memory traces from one into another instance of BAS

Known issues in **Automation Interface 3.25 SR2** that will be resolved in future:

Bug ID	Description	Current workaround
-	-	-